

Initiate a Connection in Script Mode for Zendesk

Last Modified on 01/15/2026 7:17 pm EST

Important: You cannot toggle between the different modes. To do so, you need to create a new Connection in Visual mode, Script mode, or Basic mode.

Note: Before you set up a Connection in Script mode ensure that:

- your instance is public.
- you are either in the Evaluation (trial) period or have a Paid license.


Initiate a Connection in Script Mode from Zendesk

Note: It doesn't matter which side you start initiating the Connection from. The Exalate UI remains the same. If you are initiating the connection you become the source and the other side becomes the destination.


1. Navigate to the **Connections** tab in the Exalate console.

To navigate to the **Connections** tab:


1. Click **Exalate** in the list of apps.



2. Click **Connections**.




2. Click **Initiate Connection**.



3. Enter the **Destination Instance URL**.

The **Destination Instance URL** is the link to the instance you want to set up a connection with. You can directly enter the link of that instance or the **Exalate URL** from the **General Settings** tab in the Exalate admin panel.



Exalate will suggest available Configuration Modes based on the destination instance.

4. Select the Configuration Mode. In this case, **Script Mode**.

Initiate connection x

Destination instance URL !

✓
I don't have a URL

Choose the configuration type

Basic

- Automatic configuration of basic fields
- Sync rules cannot be edited
- Only Issues can be synced
- Recommended for use cases of basic complexity

Visual

- Low-code, visual interface
- Configure both sides of the connection using a single interface
- Recommended for use cases of basic to intermediate complexity

Script

- Groovy-based scripting
- Configure each side of the connection separately
- Recommended for use cases of basic to advanced complexity

Next

5. Click **Next**.

6. Enter the Connection Information

Field	Description
Local instance short name	A short name for your instance
Destination instance short name	A short name for the destination instance
Connection name	Name of the connection
Description	Description of the connection

Initiate connection x

Connection information

Local instance short name*

Remote instance short name* ?


Connection name*

Description

◀ Previous
Next

8. Click **Next**.

9. Click **Copy invitation code**.



You can send the invitation code to the destination instance admin.

10. Click **Go to remote** to access the destination instance.

Note: When the other side accepts your invitation your connection will be activated. Refresh the **Connections** page to see the Connection status change.

What's Next?

You need to accept the Connection Invitation on the platform you want to set up an integration with. Go to the **Connections** tab in the Exalate Admin console on that platform and click the **Accept Invitation** button. Then paste the invitation code you have copied above.

Product

[About Us](#)

ON THIS PAGE

[Glossary](#) [Initiate a Connection in Script Mode from Zendesk](#)

[API Reference](#)

[What's Next?](#)

[Security](#)

[Pricing and Licensing](#)

Resources

[Subscribe for a weekly Exalate hack](#)

[Academy](#)

[Blog](#)

[YouTube Channel](#)

[Ebooks](#)

Still need help?

[Join our Community](#)

[Visit our Service Desk](#)

[Find a Partner](#)