Initiate a Private Connection in Script Mode for Jira Cloud

Last Modified on 03/20/2024 10:26 am EDT


Note: For Private Connections:

- an instance you have access to is considered a public side.
- an instance you don't have access to is considered a private side: destination instance.

The main difference between private and public connection types is whether the HTTP/HTTPS requests are initiated from one side or from both sides. In this case, HTTP/HTTPS requests are initiated from the destination's private side only.

Initiate a Private Connection from Jira Cloud

- 1. Navigate to the **Connections** tab in the Exalate console.
 - Click **Settings** \rightarrow **Apps** & click **Connections** under the **Exalate** menu.



2. Click Initiate Connection.


Connections			
Connection defines synchronization behavior, including communication details, sync rules, and scope.	Initiate connection	Accept invitation	C

3. Click 'I don't have a URL'

If the destination instance is in a private network toggle I don't have a URL.

	Initiate connection	×
Destination instance URL		
		l don't have a URL 🗸
		Next

- 4. Choose a **Script** connection mode.
- 5. Click Next.



6. Enter Connection information & Click Next

Field	Description
Local instance short name	A short name for your instance
Destination instance short name	A short name for the destination instance
Connection name	Name of the connection
Description	Description of the connection

	Initiate connection	×
Connection information		
Local instance short name*	Remote instance short name*	
	0	
• ··· •		
Connection name*		
Description		

7. Select a project for the incoming sync.

8. Click Next.

Note: As this is a Public-Private connection and you don't have admin access to the other side, you can continue to configure on your end and then send an invitation to your partner.

9. Click Copy Invitation Code

Here you can copy the invitation code and send it over to your partner. The destination side is shown as "unknown" since this is a private side.

Initiate connection	×
On the "company B" side, you (or their application administrator) need to Accept the Invitation. Use the following invitation code: Copy invitation code	
	Done

10. Click **Done**

Once your partner accepts the invitation, you can start synchronization.

Note: When the connection is set up on the Public source side, the Private side administrator

should accept the invitation in the Private-Public connection.

Glossary 🖓
API Reference 🔀
Security 🖸
Pricing and Licensing 🖸
Resources
Academy 🔁
Blog 🔁
YouTube Channel 🖸
Ebooks 🖸
Still need help?
Join our Community 🖸
Visit our Service Desk 🖸
Find a Partner 🖸