Set up a Connection in Basic Mode for Jira Onpremise

Last Modified on 03/18/2024 9:57 am EDT

Note: Before you set up a Connection in Basic mode ensure that you don't use an older version of Exalate.

Connections in Basic mode have a set of **Sync Rules**, generated by Exalate. You can sync a basic set of issue fields: summary, description, comments, attachments, and issue types.

Note that issue types are mirrored: tasks are synced as tasks, improvements as improvements, and so on. For example, when you sync epic Exalate creates either an issue with the default issue type, if the default issue type is set in the project configuration, or **Task** if not set. This also applies to any other issue type that is not found on the destination side.

All comments are synced as public comments.

Note: You cannot modify Sync Rules in Basic Mode.

If you want to edit/delete Sync Rules, you can upgrade the connection to Visual Mode or Script Mode.

Initiate a Connection in Basic Mode from Jira On-premise

Note: It doesn't matter which side you start initiating the Connection from. The Exalate UI remains the same.

1. Navigate to the **Connections** tab in the Exalate console.

Click **Settings** \rightarrow **Apps** & click **Connections** under the **Exalate** menu.

💠 Jira Software 👘 🕫	shboards v Projects v Issues v Boards v Plans v Create		🚽 🀔 😧 🗘	(
Administration	9. Search Jira admin		JIRA ADMINISTRATION	٦
Administration	< Search Sina admini		Applications	es
			Projects	
Applications Projects Issues	Manage apps User management Latest upgrade report System		Issues	
ATLASSIAN MARKETPLACE			Manage apps	
Find new apps			User management	
			Latest upgrade report	
Manage apps	Connections		System	
EXALATE	Connection defines synchronization behavior, including communication details, sy			_
Getting Started	rules, and scope.	mc Initiate connection Accept invitat	ion 🛛 📿	
General Settings				
Connections				
Errors	Connection Entities under syn	c Last sync Status		
Bulk Connect				

2. Click Initiate connection.

Connections			
Connection defines synchronization behavior, including communication details, sync rules, and scope.	Initiate connection	Accept invitation	c

3. Enter the **Destination Instance URL**.

The **Destination Instance URL** is the link to the instance you want to set up a connection with. You can directly enter the link of that instance or the **Exalate URL** from the **General Settings** tab in the Exalate admin panel.

$\ensuremath{\textbf{Note}}$: If you enter the URL of your own instance here,	Exalate determines it's a local
connection between 2 projects within your instance.	

	initiate c	onnection	
Destination instance URL			l don't have a URL 💙

Exalate suggests available Configuration Modes based on the destination instance.

- 4. Select **Basic**.
- 5. Click Next.
- 6. Select a project where you would like to sync entities received from the destination side.

Ini	tiate connection		×
elect a project for the incoming sync			
xalate generates default sync rules to synchronize basic	issue fields. By default the following	issue data will be synchron	ized:
ummary, description, comments, attachments and issue	types.		
lease select the project where you want to create iss	ues, received from the other side*		
Select Project	~		

7. Click Next.

8. Confirm if you have admin access to the destination instance.

Further steps are different if you have or don't have admin access to the destination instance.

- Select **Yes, I have admin access** if you have admin access to the destination instance. You are redirected to the destination instance to establish a connection.
- Select No, I don't have admin access if you don't have admin access to the destination instance. You generate an invitation for the destination instance admin so they could establish a connection on their end.

onnection
 No, I don't have admin access You will generate an invitation and send it to the destination instance admin to establish the connection
connection

Steps for: Yes, I have Admin Access

Click Yes, I have admin access & Initiate the connection.

Note: You will be required to verify access on the destination instance. After that, complete the following steps on the destination instance.

9. Select the project or repository where you want to sync entities.

Note: Selecting the project or repository is not applicable to all platforms. In this case, the Connection is established after the previous step.

	Accept invitation ×	
	Select a project for the incoming sync After accepting an invitation for a Basic mode connection, Exalate will be able to sync basic issue fields. The sync rules cannot be updated. Exalate will sync the following issue data: summary, description, comments, and attachments. Issue types are mirrored. This means that tasks will be synced as tasks, bugs as bugs, and improvements as improvements. If an issue type is not included in the basic set, it will be synced as a task.	
	Please select the project where you want to create entities, received from the other side.*	
	Select Project	
	Previous Confirm	
10. Click Confir	m .	
The Connection	has been set up.	
	Exalate ×	
	Connection established successfully ✓ Sync your first issue to see how it works.	
	Please enter an issue key from the project Test (TEST) to proceed	

Exalate

No, I don't have Admin Access

Click No, I have admin access & Initiate the connection.

9. Click Copy invitation code.

You can send the invitation code to the destination instance admin.

On the "company B" side, you (or their application administrator) need to Accept the Invitation. Use the following invitation code: Copy invitation code	Initiate connection	×
	Invitation. Use the following invitation code:	

10. Click Done.

Note: The following steps must be completed on the destination instance.

11. Click on **Accept Invitation** under the **Connections** tab in the Exalate Admin Console in the destination instance and Paste the invitation code.

	1ZpdGF0aW9uU2VjcmV0ljoiNUI2SnpGckZHZGhqZlNrVGlQb1NKN3pablp0clV3MWUiLCJpbnZpdGVkSW5zdGFuY2VVaWQiC
	DYwYmE2Yy0xNTg5LTQxNDUtYTk2MS03MGlzNWUyMjgzZjQiLCJub2RISW5mbyl6eyJuYW1lljoibmFib28iLCJiYXNIVXJsljoiaH
	VI6Ly9qY2xvdWRub2RILWxxZ2Ytb3Zzei14c250LXFicmEuZXhhbGF0ZS5jbG91ZCIsImIzc3VIVHJhY2tlcIVybCl6Imh0dHBzOi8v
	28uYXRsYXNzaWFuLm5ldClsIm5vZGVUeXBIIjoiSkISQV9DTE9VRClsImIzc3VIVHJhY2tlcIZlcnNpb24iOil3LjAuMClsIm5vZGVB
	ZXJzaW9uljoiNy4wLjAiLCJub2RlVmVyc2lvbil6ljUuMy4zliwiZXhhbGF0ZVBsdWdpblZlcnNpb24iOil1LjMuMylslm1pbkh1Yk9ia
,	INWZXJzaW9uljoiMS4yLjAiLCJtYXhldWJPYmplY3RzVmVyc2lvbil6ljEuMTQuMClsIm1pblJlc3RWZXJzaW9uljoiMS4wLjAiLCJtY
	(N0VmVyc2lvbil6ljUuMi4wliwicG9sbE9ubHkiOmZhbHNILCJleGFDb21wVmVyc2lvbil6ljUuMy40liwicmF3RXhhQ29tcFZlcnNp
b24iOi	iI1LjMuNClsImluc3RhbmNIVWlkljoiODdiZWE2MWltYTk2Mi00YjdiLWl1NzUtZjE5MDRiOGU0ZDA3liwiZWRpdG9yljp7ImFkb
WluUF	JJvb2ZVcmxUZW1wbGF0ZSI6Imh0dHBzOi8vbmFib28uYXRsYXNzaWFuLm5IdC9sb2dpbj9yZWRpcmVjdENvdW50XHUwMD
NkMV:	x1MDAyNmRlc3QtdXJsXHUwMDNkaHR0cHMIM0EIMkYIMkZuYWJvby5hdGxhc3NpYW4ubmV0JTJGcGx1Z2lucyUyRnNlcn

12. Click Next.

13. Select the project where you want to sync issues.

Note: Selecting the project is not applicable to all platforms. In this case, the Connection is established after the previous step.

	Accept invitation	×
	Select a project for the incoming sync After accepting an invitation for a Basic mode connection, Exalate will be able to sync basic issue fields. The sync rules can updated. Exalate will sync the following issue data: summary, description, comments, and attachments. Issue types are mirrored. This means that tasks will be synced as tasks, bugs as bugs, and improvements as improvements. issue type is not included in the basic set, it will be synced as task.	
	Please select the project where you want to create entities, received from the other side.*	
	Select Project	
	< Previous C	Confirm
14. Click Confir	m.	
The Connection	has been set up.	
	Exalate	×
	Connection established successfully ✓ Sync your first issue to see how it works.	
	Please enter an issue key from the project Test (TEST) to proceed	
		Exalate

Start Synchronizing

You can sync your first entity in Exalate to see how it works: enter the entity URN on the previous screen and click **Exalate**.

When syncing your first entity, you see the status of your sync. The links to both entities are displayed at the bottom as shown below. You can open them up to see more details.



What's Next?

Next, you can choose to

- sit back and relax while the sync works!
- Manually synchronize entities.
- Connect an entity.
- Sync entities in bulk.
- Create a trigger.

ON THIS PAGE

 priviewet
 Connection in Basic Mode from Jira On-Abemisks [2]

 Release History [2]
 Start Synchronizing Glossary [2]

 Wth #KeseNextel [2]
 Wth #KeseNextel [2]

 Security [2]
 Pricing and Licensing [2]

 Pricing and Licensing [2]
 Resources

 Academy [2]
 Security [2]

 YouTube Channel [2]
 Ebooks [2]

 Still need help?
 Join our Community [2]

 Visit our Service Desk [2]
 Find a Partner [2]